

# **DoPE .NET – Visual Basic**

## **Starter Manual**

## DOLI Elektronik GmbH

---

<b>Firmenname:</b>	DOLI Elektronik GmbH
<b>Zentrale:</b>	Adi-Maislinger-Straße 7, 81373 München, Deutschland  (+49)-089-20 243-0 Fax (+49)-089-20 243 243 E-Mail info@doli.de
<b>Fertigung:</b>	Ulmer Straße 34, 89584 Ehingen, Deutschland  (+49)-07391-58039-0 Fax (+49)-07391-58039-71 E-Mail ehi@doli.de
<b>Vertrieb:</b>	Mühlstr. 26, 55271 Stadecken-Elsheim, Deutschland  (+49)-06130-944250 Fax (+49)-06130-944251 E-Mail sales@doli.de
<b>Internet:</b>	<a href="http://www.doli.de">www.doli.de</a>

## **Inhaltsverzeichnis**


<b>1</b>	<b>INTRODUCTION.....</b>	<b>4</b>
<b>2</b>	<b>SET UP A NEW VISUAL BASIC PROJECT .....</b>	<b>5</b>
<b>3</b>	<b>TROUBLE SHOOTING .....</b>	<b>13</b>

## 1 Introduction


This document briefly describes how to set up a new DoPE .NET application-project in Visual Basic .NET.

## 2 Set up a new Visual Basic Project


- Choose File -> New -> Project




- Under Project Types, choose Windows and under templates: Windows Forms Application
- Choose a project-name like – MyVisualBasicApplication – and click the OK-button




- **Important: Select the x86-platform configuration**
- To create a new x86 configuration, click on configuration manager




- In the platform column, click new



- Choose x86




- Ensure that the platform x86 is selected




- Copy the DoPE-Libraries (Download from: [www.DOLI.de](http://www.DOLI.de)) into your application's **source-code directory** (e.g. c:\MyVisualBasicApplication\ MyVisualBasicApplication \):
  - **DoPENet.dll**
  - **DoPE.dll**
  - **DoDpx.dll**




- In the Project-Solution-Explorer, right-click on MyVisualBasicApplication
- Select: Add Reference...




- Select the **DoPDNet.dll** file
- Click the OK-button




- In the Project-Solution-Explorer, right-click on MyVisualBasicApplication
- Select Add -> Existing Item...




- Change the filter to - All Files (\*.\*) - in the filter checkbox




- Select the highlighted DLL files shown in the window below
- Click the Add-button



- In the Project-Solution-Explorer, hold the Ctrl-key and select the highlighted DLL files shown in the window below
- In the Properties-Window, select for – Copy to Output Directory – the value – Copy Always –



- Now all preparations have been made to use DoPE .NET in your project
- In order to unlock and use the DoPE .NET library, some code has to be added
- Please double-click on the Form1-window to switch to the Form1\_Load subroutine



- Import the Doli.DoPE namespace
- Next you should declare a class-variable of the type Edc. Let's name the variable – MyEdc –
- To unlock the DoPE .NET library, a version check must be done by calling the CheckApi(version of my DoPE .NET DLL) subroutine
- After creating a new Edc object the DoPE .NET library is ready to use
- Call any DoPE-API subroutine referring to this template: MyEdc.DoPEModule.DoPEAPICommand

```
Imports Doli.DoPE

Public Class Form1
    Dim MyEdc As Edc

    Private Sub Form1_Load(ByVal sender As System.Object, ByVal e As System.EventArgs) Handles MyBase.Load
        Try
            DoPE.CheckApi("2.68")
            MyEdc = New Edc(DoPE.OpenBy.DeviceId, 0)
        Catch ex As Exception
            MsgBox(ex.ToString())
        End Try
    End Sub
End Class
```

### Final note regarding the Try-Catch-Block

It prevents your program to freeze when an unforeseen error occurs. Note that a DoPEException arises when the construction or destruction of an object of type Edc or EdcList has failed.

## 3 Trouble Shooting

- Please ensure, that the stated DoPE-version in CheckApi is equal to the file versions of the DoPE.dll and the DoPENet.dll - like displayed in the picture below
- The newest DLL files can be downloaded from [www.DOLI.de](http://www.DOLI.de)
- After you have compiled your project, the following DLLs must have been copied automatically by Visual Studio into your debug/release directory:
  - DoPENet.dll
  - DoPE.dll
  - DoDpx.dll
- If the libraries highlighted in blue are missing, please refer to the instructions on page 6
- If the libraries highlighted in green are missing, please refer to the instructions on page 8
- Ensure the x86 platform is selected (in the main-window, beneath the debug-checkbox)

